

This is a sample Reference manual only

A separate User Guide is also included in the package

EMXShip Class Properties

INPUT

Property

Notes: All basic required properties are noted with "" on their property name. Some other properties may become required depending on your shipping parameters.*

Type

Description

Notes: All default values are blank except when specified in the description.

*AccessLicenseNumber	String	The identifying number of the Access License. Also referred to Access Key.
*UserId	String	UPS User ID
*Password	String	UPS Password
*ShipperNumber	String	Shipper's account number. This is a 6-digit UPS account number.
*AccountNumber	String	UPS Account number. Must be the same UPS account number as the one provided in Shipper/ShipperNumber.
NegotiatedRatesIndicator	Boolean	NegotiatedRates option indicator. The Shipper account and UserId combination must be qualified to receive Negotiated rates. If the indicator is set to TRUE and the Shipper is qualified then Negotiated rates will be returned. Default Value: False
*ShipperName	String	Shipper's company name.
ShipperAttentionName	String	Shipper's Attention Name. Required if destination is international.
xxx	String	xxx
xxx	String	xxx
...	String	...
xxx	String	xxx

OUTPUT

error_code	String	Internal error code. Always non-zero if an error has been encountered.
error_description	String	Internal error description.
xml_confirm_response	String	The actual 'CONFIRM XML' Response
xml_accept_response	String	The actual 'ACCEPT XML' Response.
xml_void_response	String	The actual 'VOID XML' Response.

ShipmentDigest	String	Encoded shipment parameters required to be passed in the accept phase. (For advanced users.)
xxx	String	xxx
...	String	...
Package	xxx	xxx

UPackage Class

INPUT

PackageReferenceNumberCode	String	Reference number type code, for the entire shipment. The code specifies the Reference name. Valid if the origin/destination pair is US/US or PR/PR. 2 character alpha-numeric.
PackageReferenceNumberValue	String	Customer supplied reference number. Valid if the origin/destination pair is US/US or PR/PR Supports up to 2 customer supplied combinations of Reference code-value combinations.
xxx	String	xxx
...	String	...

METHODS

ShipAdd_Package()	Add a package to ship
ShipSubmit()	xxx
VoidShipment_Initiate(string ShipmentID)	Initiate a voiding transaction
xxx	xxx
xxx	xxx